




Using the ONYX v.7 Demo for Android



11 JUNE 2021



This screen will greet you when you open the app.

This applies to the Android Demo from the Google PlayStore.

HOW TO USE:

1. When you open the app, the first screen you see will be the settings screen shown at left.

2. Make your selections as to what files you want returned:

setReturnRawImage - This provides you with the raw image acquired by the phone camera for comparison.

setReturnedProcessedImage - This option will return to you our processed images, which are usually best for matching.

setReturnWSQ - This provides you with WSQ (Wavelet-Scalar Quantization) compressed images.

setReturnFingerprintTemplate - A generic fingerprint template is produced.

setUseOnyxLive - *ONYXLive* processes the image through our AI-driven liveness detection system and returns the level of confidence the system has that it is a valid fingerprint. (Requires data connection.)


setReticleOrientation:

Select "LEFT" to capture the four fingers of the left hand.


Select "RIGHT" to capture the four fingers of the right hand.

Select "THUMB_PORTRAIT" to capture a thumb image.


3. Touch the "CAPTURE" button at the bottom of the screen. The acquisition interface will launch. Position your fingers or thumb as in the images below.



Left Hand




Right Hand



Thumb

DIAMOND FORTRESS TECHNOLOGIES

+01 855 785 8646 | www.diamondfortress.com



4. Hold the phone steady, and based on the on-screen feedback, move your hand closer to or farther away from the camera lens. When asked, hold your fingers still. The app is about to capture.

7. Your print(s) will appear on the screen like in the top image to the left

8. If you scroll down to the bottom of the screen, (lower left image), you can then save the images to your phone, email them, or finish and go back to the settings screen.

